

Installing the Ultra100TX2 card on an existing NT 4.0 Operating System

*READ THIS FIRST

*Do not connect any hard drives to the Ultra66 Controller before starting this procedure, connect all drives to your motherboards onboard controller until this install procedure is complete.

-Install Procedure

- 1.) Boot Win NT up to your desktop.
- 2.) Choose "Settings" from the "Start Menu".
- 3.) Choose Control Panel from the settings Menu.
- 4.) Double click on "SCSI Adapters".
- 5.) Choose drivers and then press "Add".
- 6.) In the Install Driver dialog box, press "Have Disk".
- 7.) When the "Install from Disk" appears, insert the "Ultra100TX2 Driver" diskette in drive A:, and then choose OK.
- 8.) When the "Install Driver" dialog box appears, select "Promise Ultra100TX2 Controller NT" and then press OK.
- 9.) When the "Select SCSI adapter Option appears press "Install".

Power down and reconnect drive or drives to the **Promise Ultra100TX2 Controller**. Do not forget to check driver jumpers and BIOS settings. Our controller card is seen as **"SCSI Controller"** by the motherboard BIOS. Make proper changes so you can boot from our controller card.